


## Selecting Parts of Images

An important feature of any graphics program is its ability to select parts of images. This might include separating an image from its background or removing a background. In this chapter you will learn how to select parts of images using a variety of different tools.


### Loading a Sample Image

A sample photo will need to be opened and some editing carried out on it.

- 1 Load Photoshop Elements in EDIT MODE or close the current file.
- 2 Display the FILE menu and select OPEN.
- 3 Access the PSE7 SUPPORT FILES folder.



- 6 Press CTRL+0 to set the view to FIT ON SCREEN so that the image fills the screen.



## The Editing Tools


Photoshop Elements offers numerous ways of selecting parts of a drawing. Some of them are the basic, such as the EDIT MARQUEE TOOL and the LASSO TOOL, however, some are much more powerful, such as the QUICK SELECTION TOOL and the MAGIC WAND TOOL.

The next few exercises will show you how to apply these tools.

## The Edit Marquee


There are two edit marquees, one is rectangular and the other is an oval.

### A The Rectangular Marquee Tool




1 Move the pointer over the EDIT MARQUEE TOOL in the TOOLS palette, hold down the mouse button and the edit marquees should be displayed.

2 Select the RECTANGULAR MARQUEE TOOL.



3 Drag a frame around the cat's head.


**NOTE:** A frame of 'marching ants' is added to the screen to highlight the selection. This selected area can be moved, copied, rotated, resized, transformed and adjusted.




4 Click on the MOVE TOOL at the top of the TOOLS palette and drag the selected area.

- 5 Press CTRL+Z (or select UNDO MOVE from the EDIT menu) to return the selected area to its original position.

## B The Elliptical Marquee Tool




1 Click and hold on the EDIT MARQUEE TOOL again and select the ELLIPTICAL MARQUEE tool.




2 Click outside the selected area to deselect it then drag an frame around the cat's head. This time the selected area is an oval.

**NOTE:** When you select the EDIT MARQUEE TOOL you can press SHIFT+M to toggle between the RECTANGULAR MARQUEE and the ELLIPTICAL MARQUEE.



- 4 Press CTRL+Z to undo the move. You can also click on the UNDO button at the top right of the screen.



**NOTE:** The SHIFT causes the ellipse to be a circle. If you hold down the SHIFT key and drag the RECTANGULAR MARQUEE TOOL, a square selection area is drawn.

## Deselecting Objects

When you select an area on the screen it remains selected until you select another area. To turn a selection off:

Press CTRL+D and the selection should be removed.